Preparation

1 install AutoPro X app

Search for "AutoPro X" on Google Play Store and install it



Scan with your phone and tap the link.



2 Turn on "Wireless AA vehicle Mode"

Allow all permissions, then enable "Wireless Android Auto Vehicle Mode" in the AutoPro X app!



How to Connect

1 Remove your phone from the car.

In the Phone Projection menu, delete all paired devices.



2 Unpair your car from your phone.


In your Samsung phone, unpair your car.



3 Connect AutoPro X to the vehicle.


Connect AutoPro X to the vehicle using a cable. If it isn't recognized or the LED keeps blinking, contact support for assistance or a cable replacement.

- *Plug it into the data port.
- *Toyota/Lexus Black cable needed



Select "Use" on the popup message.

After connecting, select "**Use**" on the Android Auto popup.



5 First-time Android Auto connection required.

Select Android Auto mode on the left.

A one-time connection is needed for calls and music.



*If Android Auto won't open, go to your phone's Settings → Apps → Android Auto → Storage → Clear Data.

How to Connect

6 Connect DeX.

On the AutoPro X home screen, select AutoPro X mode on the right.

Selecting AutoPro X mode will disconnect Android Auto.



Run Samsung DeX on your smartphone.

- Option 1: Through Settings Settings → Connected Devices → Samsung DeX
- Option 2 : From the Quick Panel
 Swipe down from the top →
 Tap the DeX icon
- Option 3 : Using Bixby
 Activate Bixby → Say "Run DeX"



In the "Connect wirelessly" list, select AutoProX_OOOO.



- * Switch to DeX after Android Auto connects

 iii Apps in the bottom left corner → Tap the first app(logo)
- * Switch to Android Auto after DeX connects

 ∴ Apps in the bottom left corner → Tap 'Exit DeX'

 (or tap the DeX on your phone to exit)

Just follow along!

Video User Guide



For wireless Android Auto cars,

Video User Guide



Android Auto Cars

For Wireless

Please check!

Change font size and screen zoom!

Video User Guide



How to switch mode!

Video User Guide





AutoPro X